

Setting up a Plot to File Driver for Brownie's Digital Imaging

1. Open your Autodesk AutoCAD software and open your drawing.
2. Go to your "Tools" drop down menu
3. Choose "Wizards"
4. Choose "Add Plotter"
5. Introduction Page:
 - a. Click the "Next" button
6. Begin:
 - a. Highlight the "My Computer" button
 - b. Click the "Next" button
7. Plotter Model:
 - a. Under the "Manufacturers" menu, highlight "Hewlett-Packard"
 - b. Under the "Models" menu, highlight "DesignJet 755CM C3198A"
 - c. Click the "Next" button
8. Driver Information pop-up:
 - a. Click the "Continue" button
9. Import Pcp or Pc2:
 - a. Click the "Next" button
10. Ports:
 - a. At the top of the screen, highlight the "Plot to File" button
11. Plotter Name:
 - a. Name the new plotter: **Brownies Plot File**
 - b. Click the "Next" button
12. Finish:
 - a. Click the "Finish" button

Creating Plot Files for Brownie's Digital Imaging

1. Open your AutoCAD software and open your drawing.
2. Go to your "File" drop down menu and choose "Plot..." or type "plot" on the command line
3. Plot:
 - a. Select the "Plot Device" tab
 - b. In the "Plotter configuration" section, select the "Brownies Plot File.pc3" driver
 - c. In the "Plot to file" section, make sure that the "Plot to file" box is checked and specify
4. the name and location of your plot file
 - a. Select the "Plot Settings" tab
 - b. In the "Paper size and paper units" section, select your paper size
 - c. In the "Plot scale" window, select your scale
 - d. Click the "Full Preview" button
5. If this drawing looks correct to you, right-click on your mouse and choose "Plot"
6. This new plot file will be located in the same folder as your original .dwg file, unless you specified another folder. This new plot file is the file that you send to Brownie's.

If you have any problems, please contact the PlanWell™ department at Brownie's.

Phone: (916) 325-2234

Email: planwell@browniesrepro.com

CENTRAL

1322 V Street
Sacramento, CA 95818
(916) 443-1322
(800) 942-COPY
(916) 442-5305 FAX

ROSEVILLE

1000 Sunrise Avenue
Roseville, CA 95670
(916) 782-8000
(800) 326-8001
(916) 782-8508 FAX

JUNIOR

3235 Sunrise Boulevard
Rancho Cordova, CA 95661
(916) 635-COPY
(800) 628-6305
(916) 635-3965 FAX

RENO

3515 Airway Blvd. #203
Reno, NV 89511
(775) 853-6005
(775) 853-6008 FAX